# Using an Envelope and Matrix Code PBO Lab TRACE 3-D Example Set 1

George H. Gillespie

G. H. Gillespie Associates, Inc. P. O. Box 2961 Del Mar, California 92014, U.S.A.

Presented at

King Abdulaziz City for Science and Technology (KACST)
Riyadh, Saudi Arabia
October 2014

# Outline- Part II - Example Set 1

- ⇒ Will use PBO Lab TRACE 3-D Module to work through some examples
- 1. FODO Lattice (Focusing Quad Drift Defocusing Quad Drift)

pp 3-7

2. Finding the Matched Beam (Ouput=Input) for a Given FODO Lattice

pp 8-14

3. Finding a FODO Lattice (Quads) for a Given Matched Beam Requirement pp 15-25

1. Setup a PBO Lab "template" with Global Parameters for the following beam:

Particle Mass: Protons

Beam (Kinetic) Energy: 2.5 MeV

Frequency: 402.5 MHz

Add a "Beam" to the Model Space. Label it (Comment) "Beam\_0"

Open the "Beam" and set the Beam Parameters switch to the setting "Courant-Synder (Twiss) - Beam 2"

Set the horizontal and vertical emittances both to:  $0.0015 \frac{\pi\text{-cm-mrad, rms}}{}$ 

⇒ Save this setup as "Setup\_1" (File: Setup\_1.pbol)

We will use Setup\_1 as the starting point for several examples

# Starting with Setup\_1 construct the following FODO lattice:

Drift "D1" 20 cm long

Quad "Q1" 10 cm long 20 T/m field gradient

Drift "D2" 40 cm long


Quad "Q2" 10 cm long -20 T/m field gradient

Drift "D3" 20 cm long

### Add a "Final" element to the end of the beamline

⇒ Save this example as "Setup\_1\_FODO\_1"


Example "Setup\_1\_FODO\_1" should look (something) like this:



Use the menu chain: Commands->TRACE 3-D->Graph Beam Line


⇒ Result Does Not Look So Pretty! Let's Find Some Scales

# Use the menu chain: Commands->TRACE 3-D->Options A window titled "Trace 3-D Options" should open:



**Check box "Use Automatic Graph Scales"** ⇒ numbers change

# Use the menu chain: Commands->TRACE 3-D->Graph Beam Line



- ⇒ Well, Still Not "Pretty," But Most Data Now Visible
- ⇒ Save this updated example (same name "Setup\_1\_FODO\_1")

Go back to the "Trace 3-D Options" window and uncheck the box "Use Automatic Graph Scales"

⇒ Don't want the plot scales changing every time we run!


Finding Matched Beam for a FODO Lattice (1st Attempt)

2a. If Necessary Set the Context Switch to TRACE 3-D

**Open the Final Piece** 

Use the "Open" button under the Constraints panel

For "Beam Matching" - "Vary Initial Beam to Find Matched Beam" Select the Option: "1 Matched beam in X, Y planes"




Then use the button "Perform Matching"

OK

## Finding Matched Beam for a FODO Lattice (1<sup>st</sup> Attempt)

You may get something that looks like an error dialog Just click OK!

You can continue to ask TRACE 3-D to search for a solution, using the "Perform Next Matching" button. The Mismatch Factor will improve, but won't get below about 13.5 or so.



Trace 3D may have terminated

PBO-Lab

# What's happening here?


This FODO lattice does not have a matched beam solution.

- ⇒ the lattice is "unstable" an "unmatchable" FODO lattice
- ⇒ Is there a quick way to know this in advance?

## Finding Matched Beam for a FODO Lattice (1<sup>st</sup> Attempt)

**Use menu: Commands->TRACE 3-D->Calculate Phase Advance** 

You will a text file output window named "Trace 3-D History" that will have virtually nothing in it:



TRACE 3-D first attempts to calculate the phases advances, called "SIG" in this text output. TRACE 3-D "SIG" is in degrees.

The lack of data means that the phases advances are complex, i.e., the lattice for the beamline is unstable (all 3 phase planes).

⇒ Leave the "Trace 3-D History" file window OPEN

# Finding Matched Beam for a FODO Lattice (2<sup>nd</sup> Attempt)

2b. Start over from the Setup\_1\_FODO\_1, but now reduce the strengths of the quads. Try these

Quad "Q1" 10 cm long +10 T/m field gradient Quad "Q2" 10 cm long - 10 T/m field gradient

First: Use the TRACE 3-D Command to Graph Beam Line.

**Next:** Use the TRACE 3-D Calculate Phase Advance.

Do you think you can find a matched beam now?

2c. Reduce the strengths of the quads further:

Quad "Q1" 10 cm long +5 T/m field gradient Quad "Q2" 10 cm long - 5 T/m field gradient

First: Use the TRACE 3-D Command to Graph Beam Line.

**Next:** Use the TRACE 3-D Calculate Phase Advance.


Do you think you can find a matched beam now?

⇒ When you get "SIG" values, save as "Setup\_1\_FODO\_2"

## Finding Matched Beam for a FODO Lattice (2<sup>nd</sup> Attempt)

"Setup\_1\_FODO\_2"

# The "Trace 3-D History" file should look something like this:



In addition to the X and Y Phase Advances (SIG), TRACE 3-D also computes the X and Y Twiss Parameters for the matched beam (ALPHA, BETA).

# Why no data for Z?

Have the matched beam parameters, but the data are not yet in the Beam Piece for other calculations ⇒ Copy & Paste numbers?

### **Finding Matched Beam for a FODO Lattice**


"Setup\_1\_FODO\_2"

(Quad "Q1" 10 cm long +5 T/m field gradient)

(Quad "Q2" 10 cm long - 5 T/m field gradient)

# 2d. Use the TRACE 3-D Command: Perform Matching

You should get these matched beam parameters:




 $\alpha_{\rm X}$   $\beta_{\rm X}$  (m/rad)  $\alpha_{\rm Y}$   $\beta_{\rm Y}$  (m/rad) -1.246384 1.002772 1.246384 1.002772

- ⇒ Change the Beam Piece Comment to "Beam\_1"
- ⇒ Save this example as "Setup\_1\_FODO\_2\_Matched"

### **Finding Matched Beam for a FODO Lattice**

# 2e. Use the TRACE 3-D Command: Graph Beam Line You should now get a typical "matched beam" envelope display:



# We will Find the Quad Strengths to Transport a Given Beam

- ⇒ If you have not already done so, close & reopen PBO Lab
- 3. Open the two (2) PBO Lab Files previously saved:

```
"Setup_1_FODO_1"
"Setup_1_FODO_2_Matched"
```

In the model "Setup\_1\_FODO\_2\_Matched" select (highlight via mouse) "Beam\_1" Piece, and then use Edit->Copy

Switch to the model "Setup\_1\_FODO\_1" and use Edit->Paste

⇒ Beam Piece should appear on the Work Space

Move Beam Piece to the Model Space of "Setup\_1\_FODO\_1"

Delete the "old" Beam\_0" Piece from the Model Space

Close the model "Setup\_1\_FODO\_2\_Matched"

- ⇒ This is just to avoid any confusion!
- ⇒ Save the new example as "Setup\_2\_FODO\_1"


# Finding a FODO Lattice for a Matched Beam Requirement "Setup\_2\_FODO\_1"

### 3a. Open the "Q1" Quad Window

Make Sure the Quadrupole Strength selection is set to Field Gradient

Select the "S" button that is to the left of Magnetic-Field Gradient

You should see a window like this
On the TRACE 3-D panel select Match Variable
"MTCH1" will appear as a Symbolic Parameter Name
Close this "S" window & the "Q1" Quad Window



⇒ Save this updated example (same name "Setup\_2\_FODO\_1")

"Setup\_2\_FODO\_1"

### 3b. Open the "Q2" Quad Window

Select Magnetic-Field Gradient "S" button

Then select Couple to Match Variable and select the "MTCH1" choice


(only one available)

The window should look like this

The Couple to Match Variable set to "MTCH1

What to set for Coupling K Factor?


For now leave a "+1" choice



### Close this "S" window & the "Q2" Quad Window

⇒ Save this updated example (same name "Setup\_2\_FODO\_1")

3c. Open the Final Piece window and select Final Beam button




At This Point, One Could Enter the Desired Matched Beam Parameters: i.e. Open the Initial Beam, Copy  $\alpha$  and  $\beta$  Values into Final Beam window

### But There is an Easier Way Using a PBO Lab Feature

The Desired Matched Beam Parameters are Already in the Initial Beam

Use the "Copy from Initial" Button to Automatically Fill in the Data

Also Select
"AutoScale
Plots"
Button



## Open Initial Beam Piece to Confirm that Initial and Final Beams Same

⇒ Save this updated example (same name "Setup\_2\_FODO\_1")

## To This Point Have Set Up:

- Match ("Vary") Parameters (Quad Strengths to Vary & Couple)
- Desired Matched Beam (Final  $\alpha$ 's and  $\beta$ 's = Initial  $\alpha$ 's and  $\beta$ 's)

# Last Step in Set Up is to Specify the TRACE 3-D "Match" Type:

⇒ PBO Lab menu chain: Commands -> TRACE 3-D -> Match Specification:


Match Specification:

Opens Window for >

**Match Specification** 

Select the Option:

"8 Fit beam in X, Y planes"




- ⇒ Save this updated example (same name "Setup\_2\_FODO\_1")
- ⇒ Do Not Execute "Perform Matching" Yet

# Look at the "Setup\_2\_FODO\_1" beam envelopes ⇒ Use the TRACE 3-D Command: Graph Beam Line

You should get an envelope display something like:

Current
Quad
Settings
Do Not
Preserve
Beam


Keep This Window Open for Future Use



### 3d. Use the menu chain:

Commands -> TRACE 3-D -> Perform Matching


You should get a window that looks (something like) this:



Solution Not Very Good on First Attempt Note MMF >> 0

We Will Iterate on this Solution To See If It Improves

Select Button "Perform Next Matching"  $\Rightarrow$  Repeat This Several Times Watch How the MMF Changes - After 4 or so Iterations You Should Get:




⇒ Save this example as "Setup\_2\_FODO\_2\_Fitted"

Let's Compare "Setup\_2\_FODO\_1" & "Setup\_2\_FODO\_2\_Fitted"

⇒ Use the TRACE 3-D Command: "Trace On Background"

**Envelopes for "Setup\_2\_FODO\_2\_Fitted" Over Lay Prior Ones:** 

New Quad Settings Do Preserve Beam



# **Examples 2 and 3 Solve Two Different Types of Problems**

Are the results for "Setup\_2\_FODO\_2\_Fitted" consistent with the results from 2.d (saved as "Setup\_1\_FODO\_2\_Matched")?

- 3e. For the file " Setup\_2\_FODO\_2\_Fitted"
- ⇒ Use the menu chain: Commands->TRACE 3-D->Options
- 3f. Open the file "Setup\_1\_FODO\_2\_Matched" (from 2.d)
- ⇒ Use the menu chain: Commands->TRACE 3-D->Options

# You should have virtually identical TRACE 3-D Beamline Plots

- In example 2 the Quad strengths were reduce until a stable FODO was obtained, then the Matched Beam was found.
- In example 3 the Quad strengths were solved for a stable FODO that corresponded to a given Matched Beam.